



Agilent Technologies

Soft Token Install and Activation Instructions

To gain access to the Agilent Technologies internal network from a remote location each user is required to have an activated RSA SecurID Token which, after proper setup, will provide the user with a temporary numeric key to be used as their password during each login.

The following document provides step by step instructions to install an RSA SecurID Software Token (Soft Token) to a PC and then to use the unique Soft Token Activation Code* to activate the newly installed token to become operational with Agilent's secure internal network.

Soft Token Install and Activation Instructions

Confirm Initial Requirements

- a. Should have Administration Permissions to PC and Internet Access
- b. Not connected to any Virtual Private Networks (VPNs)

Note: If the system already has the RSA installed, please follow steps from Activation instruction and skip the Installation instruction mentioned below

Installation Instruction

- 1) Download Soft Token Installation Wizard
 - a. Navigate web browser to webpage: <ftp://ftp.agilent.com/BPNAI/RSASecurIDToken410.msi>
 - b. Select **"Save"** to save the file "RSASecurIDToken410.msi" to your PC
- 2) Complete Soft Token Installation Wizard (Options will vary slightly for Windows XP/Vista and Windows 7)

Windows XP/Vista:

- a. Open file "RSASecurIDToken410.msi"
- b. Select **"Run"**
- c. Select **"Next"**
- d. Choose proper Region and Select **"Next"**
- e. Select to "Accept" terms of the license agreement and Select **"Next"**
- f. Select "Typical" installation and **"Next"**
- g. Select **"Install"**
- h. Select **"Finish"**

Windows 7:


- a. Open file "RSASecurIDToken410.msi"
- b. Select **"Next"**
- c. Select **"Modify"** and **"Next"**
- d. Select **"Next"**
- e. Select **"Install"**
- f. Choose to Allow and Select **"Yes"**
- g. Select **"Finish"**

Activation Instruction

3) Launch the inactive Soft Token (Select “Start > All Programs > RSA SecurID Token > RSA SecurID Token”)

4) Delete Token (If you have the fresh installation of RSA, skip this step and proceed from step 5)

- a. Click “Options”
- b. Select “Manage Token”
- c. Select “Delete Token”
- d. Click “Yes” and “OK”
- e. Click “Yes” to Import New Token



5) Activate Soft Token

- a. Look for the token seed file which you have saved on your desktop (the **.sdtid** file attached in the notification email)
- b. Double click and execute the **.sdtid** file
- c. The soft token will get configured and will prompt to enter the pin
- f. Use the same old pin to generate the token code and use the code to login through the remote access page that you usually use

6) Install and Activation Complete

After Installing and Activating your Soft Token:

Connect to Agilent by following the [Remote Access Connection Guide](#) (.pdf)

(URL: <ftp://ftp.agilent.com/BPNAI/Remote%20Access%20Connection%20Guide.pdf>)